


How to install the new NorReview & NorXfer software on your PC

1. First make a note of the version you have installed and then remove your hardlock dongle from your PC!
2. Uninstall the old version of NorXfer and NorReview and then restart the computer
3. Download software files from Norsonic.com/downloads
 - You must install the same versions i.e.1020 v6 & 1026 v6.
 - You will be asked for your name and email to download the files
4. Install the software in this order:
 1. Nor1020 NorXfer software
 2. Nor1026 NorReview software
5. Start-up NorReview and insert your USB hardlock dongle into the PC to activate the software.
6. If you do not have a USB Hardlock Dongle
 - ✓ You'll need to enter the supplied activation codes which came with the meter on the delivery note.


7. How to enter your activation codes

First run NorReview as an administrator – Right click the icon



Enter your new codes into the registration window

If you are trialling the software, enter 'DEMO' into the fields and click Register



Can't see the registration window? = Go to Help > About > Register / Install options

Need support? Call Campbell Associate on **01371 871 030**

Please setup the NorReview properties

Please login to the PC as the local user (officer), run the software as normal*

*you might need administrator rights to complete these steps.




Setting Up Your NorReview Display

Right-click on the top grey panel to open the sub-menu. Enable the following views:

- ✓ View
- ✓ Marker
- ✓ Marker Management

Move the icons onto one line




1



Setting Up the Legend

1. Select View
2. Select Legend





2

Audio Recording Playback

To set the playback of audio recordings to NorReview Player
Instead of Windows Media Player go to:

1. Select **T**ools
2. Select **O**ptions



Need to set your Percentiles? L10 & L90

Go to the Percentiles tab in the options menu

Wav-file amplification

You can increase the audio output up to 500%

Saving the settings to Default

To set the settings in NorReview as the **default**

1. Select **V**iew
2. Select **D**efault Properties
3. Select **S**et

Your settings will be automatically set next time you load up NorReview.

